



## Configuring Your E-mail Client

by Michael Foster, STC Network Systems

Here's how you can set up to read your [Your Domain](#) e-mail:

-----  
**If you use Microsoft® Outlook Express:**

You need to set up an account:

Tools -> Accounts -> Add -> Mail

Display Name: [Sample Useri](#)

E-mail Address: [sample.user@yourdomain.com](mailto:sample.user@yourdomain.com)

My Incoming Mail is a "POP3" server

Incoming mail (POP3) Server: [www.yourdomain.com](http://www.yourdomain.com)

Outgoing mail (SMTP) Server: [www.yourdomain.com](http://www.yourdomain.com)

Account name: [su@yourdomain.com](mailto:su@yourdomain.com)

Password: [xyz123](#) [note upper case letter(s) and at least one numeric character] Your login is [su@yourdomain.com](mailto:su@yourdomain.com). \* Your password is "[xyz123](#)".

Remember Password: [  ] [checked]

Login using Secure Password Authentication (SPA): [  ] [unchecked]

Finished

You can also use the Web Mail interface via your browser (just like Yahoo or Gmail) by going to your Website: [www.yourdomain.com/mail](http://www.yourdomain.com/mail), using the login as the "Username" and the password as shown above.

On that screen, you can send and receive mail AND set up your Preferences to show your real name, position, etc. DO NOT USE YOUR LOGIN E-MAIL AS YOUR RETURN OR "REPLY-TO" ADDRESS.

---

**For Qualcomm's Eudora e-mail program:**

Click on Tools -> Personalities. Then right click on the top item, "<Dominant>", and choose "New".

Account Settings: [  ] Create a brand new email account

Click Next

Personality Name: [Your Domain](#)

Click Next

Personal Information: Your Name: [Sample User](#)

Click Next

E-mail Address: [sample.user@yourdomain.com](mailto:sample.user@yourdomain.com)

Click Next

User Name: [su@yourdomain.com](mailto:su@yourdomain.com) (or [su+yourdomain.com](mailto:su+yourdomain.com))\*

Click Next

Incoming Server: [www.yourdomain.com](http://www.yourdomain.com)

POP [  ] IMAP [  ]

Click Next

Outgoing Server: [www.yourdomain.com](http://www.yourdomain.com)

[  ] Allow Authentication

Click Next

Finished!

Notes:

**Mail Server Username:** [su@yourdomain.com](mailto:su@yourdomain.com) (or [su+yourdomain.com](mailto:su+yourdomain.com))\*

**Incoming Mail Server:** [www.yourdomain.com](http://www.yourdomain.com)

**Outgoing Mail Server:** [www.yourdomain.com](http://www.yourdomain.com) (server requires authentication) **port 50**

**Supported Incoming Mail Protocols:** POP3, POP3S (SSL/TLS), IMAP, IMAPS (SSL/TLS)

**Supported Outgoing Mail Protocols:** SMTP, SMTPS (SSL/TLS)

\* If this login or "username" does not work in Outlook, try [su+yourdomain.com](mailto:su+yourdomain.com) with a plus ("+") sign instead of the at ("@") sign.

---

### Logging into Webmail

You can use your browser to log in to Webmail and send e-mail directly from the Web site:

<http://www.yourdomain.com/mail>

Enter **Username:** [su@yourdomain.com](mailto:su@yourdomain.com)

Enter **Password:** [xyz123](#)

If you cannot log in via the Web, it's not you specifically. You probably have the "Cookies" settings set extremely high to prevent Web sites from storing information on your local PC.

Then try it again.

---

### If you're using Internet Explorer:

You need to go into Tools -> Internet Options -> Privacy -> Web Sites -> Edit

Enter the "Address of Web site" as "[yourdomain.com](http://yourdomain.com)" and click on "Allow".

---

### If you use Mozilla Firefox:

Go to Tools -> Options -> Privacy -> Cookies -> Exceptions

Enter the "Address of web site" as "[yourdomain.com](http://yourdomain.com)" and click on "Allow".

-or-

Check "Allow Sites to Set Cookies"

---